

IBM Informix 4GL

Installation Guide

Version 7.31
January 2002
Part No. 000-8772

Note:
Before using this information and the product it supports, read the information in the appendix entitled "Notices."

This document contains proprietary information of IBM. It is provided under a license agreement and is protected by copyright law. The information contained in this publication does not include any product warranties, and any statements provided in this manual should not be interpreted as such.

When you send information to IBM, you grant IBM a nonexclusive right to use or distribute the information in any way it believes appropriate without incurring any obligation to you.

© Copyright International Business Machines Corporation 1996, 2002. All rights reserved.

US Government User Restricted Rights—Use, duplication or disclosure restricted by GSA ADP Schedule Contract with IBM Corp.

Table of Contents

In This Guide	1
System Requirements	2
Memory and Disk Space Requirements	2
Order of Installation	4
Establishing the Informix User, Group, and Directory	5
Setting Informix Environment Variables	7
Creating and Using a Setup File	8
Installing INFORMIX-4GL	9

Appendix A Notices

In This Guide

This guide explains how to install your INFORMIX-4GL software. It includes the following sections:

- System requirements
- Order of installation
- Establishing the Informix user, group, and directory
- Setting Informix environment variables
- Installing INFORMIX-4GL

INFORMIX-4GL includes a demonstration database called **stores7**. For information about how to build this sample database and examples, see *INFORMIX-4GL by Example*.

If you are also installing a database server, you will need to install your database server after you have installed INFORMIX-4GL. For more information, check the *Administrator's Guide* for your database server.

System Requirements

Informix provides two implementations of 4GL:

- The INFORMIX-4GL C Compiler, which uses a preprocessor to generate INFORMIX-ESQL/C source code. This code is preprocessed in turn to produce *C source code*, which is then compiled and linked as object code in an executable command file.
- The Rapid Development System, which uses a compiler to produce *pseudo-machine code* (called P code) in a single step. You then invoke a *runner* to execute the P-code version of your 4GL application. This version is sometimes abbreviated as RDS.

4GL also includes an Interactive Debugger.

This section describes the disk space and memory requirements for the INFORMIX-4GL C Compiler, the Rapid Development System, and the Interactive Debugger.

Memory and Disk Space Requirements

The following table indicates how much RAM is required, based on the number of users.

Number of Users	RAM Requirements
Small multiuser (1-10 users)	8 megabytes
Large multiuser	16 megabytes +

The following table lists the memory requirements of the various 4GL products.

4GL Component	Memory Required
INFORMIX-4GL C Compiler	
■ Programmer's Environment (i4gl)	3 megabytes + database server
INFORMIX-4GL Rapid Development System	
■ Programmer's Environment (r4gl)	3 megabytes + database server
■ P-code runner (fglgo)	3 megabytes + database server
INFORMIX-4GL Interactive Debugger	
■ Development	3 megabytes + database server

The following table lists the disk-space requirements of the various 4GL products.

4GL Component	Disk Space Required
INFORMIX-4GL C Compiler	
■ Development	85 megabytes* (size of .tar file)
■ Runtime	17 megabytes (size of .tar file)
INFORMIX-4GL Rapid Development System	
■ Development	68 megabytes* (size of .tar file)
■ Runtime	20 megabytes (size of .tar file)
INFORMIX-4GL Interactive Debugger	
■ Development	38 megabytes (size of .tar file)
Combined installation of above three products	
■ Development	100 megabytes*

* Includes 34 megabytes of Asian-language demonstrations, which might not be required.



Important: To run the 4GL compiler, you must have a C compiler installed on your computer. A C compiler is not included with this product.

Order of Installation

If you install more than one Informix product, you must install them in a specific order, as follows:

1. **Application development tools**
Install application development tools in order, from oldest to newest versions.
2. **SQL application programming interfaces (APIs)**
Install SQL APIs in order, from oldest to newest versions.
3. **Database servers**
Install database servers in order, from oldest to newest versions. Generally, a database server should be installed in the same directory as any SQL API or application development tools that use it. Therefore, verify that `$INFORMIXDIR` is set to the common directory before you install these types of products.
4. **Additional products**
Install remaining interface and documentation products in order, from oldest to newest versions.

Components of IBM Informix Client SDK 2.70 are installed during INFORMIX-4GL installation. On 32-bit platforms, components of Client SDK 2.70.UC3 will be installed; on 64-bit platforms, components of Client SDK 2.70.FC3 will be installed. Client SDK components enable developers to write applications in the language they are familiar with, such as Java™, C++, C, or ESQL.

To use the full suite of Client SDK components, you must install Client SDK 2.70. On 32-bit platforms, you must install Client SDK 2.70.UC3; on 64-bit platforms, you must install Client SDK 2.70.FC3.

You may install IBM Informix Client SDK 2.70 and INFORMIX-4GL in the same directory.

To install Client SDK and 4GL in the same directory

1. Uninstall your existing version of Client SDK.
2. Install INFORMIX-4GL according to the instructions in [“Installing INFORMIX-4GL” on page 9](#).
3. Install Client SDK 2.70.xC3 or later as appropriate.
For installation instructions, see the *IBM Informix Client Products Installation Guide*.

For more information about IBM Informix Client SDK 2.70, see the documentation set at www.informix.com/answers.

Establishing the Informix User, Group, and Directory

If this is the first time that you will install an IBM Informix product on your computer, you need to create new user and group accounts and create a new directory. Before you begin, keep the following considerations in mind:

- Know who you are logged in as. Typically, you need to be able to log in as the following users:
 - Informix: to run the Informix servers and software.
 - Yourself: to perform administrative work on your computer, such as copying or untarring files.
 - Root: to edit system files and install the Informix software.
- The user **informix** is the database equivalent of the UNIX **root** account, so anyone logged in as **informix** can completely access any Informix products and databases. Make sure you keep the password for user **informix** confidential.
- IBM Informix products use group **informix** internally to control database access. You should make user **informix** the only member of group **informix**. If you make a user of an Informix product a member of group **informix**, you can cause unintended and uncontrolled database access.

- If you are using a network, make sure you propagate the new user name to all the systems on the network. For example, you (or the network administrator) might need to run the **yppmake** utility.
- Although IBM Informix uses **/usr/informix** as the directory path and name, you can install the software in any directory. If you decide to use a different directory, substitute that directory path and name throughout this guide whenever you see **/usr/informix**.

To establish the Informix user, group, and directory

1. Create a new group called **informix** in the **group** file (**/etc/group** on most UNIX-based systems).

Generally, you should provide an unused group number greater than or equal to 100. If necessary, see your system administrator or operating-system manual for assistance.

2. Add a new user called **informix** to the **/etc/passwd** file and assign the user to the group **informix**.

Generally, you should provide a user ID number greater than or equal to 100 for that user and include a password for user **informix**.

3. Create a new directory for your 4GL software by entering a command such as the following:

```
mkdir /usr/informix
```

Setting Informix Environment Variables

Before you can use any IBM Informix product, the following environment variables must be set correctly:

- **INFORMIXDIR:** the location of the client programs, library files, message files, header files, and other IBM Informix software components. For example:

```
setenv INFORMIXDIR /extra/4gl
```

- **PATH:** the location of the binaries for your Informix software. For example:

```
setenv PATH ${PATH}:/extra/4gl/bin
```

- **INFORMIXSERVER:** the arbitrary, logical name you supplied for your Informix database server. This name is used to establish connectivity in client/server configurations. For example:

```
setenv INFORMIXSERVER cardtrick_01
```

- **INFORMIXSQLHOSTS:** the path to the **etc/sqlhosts** file within your Informix database software. For example:

```
setenv INFORMIXSQLHOSTS /extra/4gl/etc/sqlhosts
```

- **LD_LIBRARY_PATH:** sets the path to the library file that the Informix database software uses:

```
setenv LD_LIBRARY_PATH $INFORMIXDIR/lib:4INFORMIXDIR/lib/  
esql:$INFORMIXDIR/lib/tools
```

For more information about setting IBM Informix environment variables, see the *IBM Informix Guide to SQL: Reference*. If you need to make modifications to the **termcap** file, make those modifications in another directory and reference that directory.

Creating and Using a Setup File

You can create a setup file that stores the environment variables. You must run the environment variables in the window from which you are running an IBM Informix product. You can then source the file to apply the environment variables.

To create and use a setup file

1. Create a setup file using either the **Text Editor** or **vi** editor.
2. Enter your current environment variables into the setup file. For example, a setup file might include the following environment variables:

```
setenv INFORMIXDIR /extra/4gl
setenv PATH ${PATH}:/extra/4gl/bin
setenv INFORMIXSERVER cardtrick_ol
setenv INFORMIXSQLHOSTS /extra/4gl/etc/sqlhosts
```

3. Save the file.
4. Each time you open a new shell window, source the setup file. For example:

```
source setup
```

5. View the environment variables to make sure they are set correctly. It is always a good idea to check the environment variables. Instances will occur where UNIX might not allow you to source a file. If this occurs, you might have to log in as another user to source the file.

```
env
```

Installing INFORMIX-4GL

This section contains instructions for loading and installing INFORMIX-4GL. If you are also installing a database server, review the installation and configuration information in the *Administrator's Guide* for your version of the database server before you proceed with the steps in this section.

Before you begin, you will need the following:

- INFORMIX-4GL software media
- Serial number keycard
- Your device name

Your IBM Informix product materials include a serial number keycard and CD-ROM or other electronic media that contain all the product files. Both are necessary for installation. If you do not have the serial number keycard or the proper media, contact your supplier or IBM Informix sales representative.

You will need the serial number keycard to perform the installation procedure that follows. Your serial number keycard provides the correct command for copying the Informix files onto the hard disk of your computer. It lists a version of the **tar** command similar to the following:

```
tar xvf[b] devicename [20]
```

where *devicename* refers to the full pathname to that device. Devices are commonly in **/dev**, so the name is normally **/dev/*devicename***.

To install INFORMIX-4GL

1. Log in as root.
2. Load the CD-ROM or other electronic media supplied with your software into the appropriate drive in your computer.
3. If you are not currently in the **\$INFORMIXDIR** directory, enter the following command:

```
cd $INFORMIXDIR
```

4. Copy the software files from the CD-ROM or other electronic media to the current directory by entering the **tar** command listed on your serial number keycard.

Depending on which 4GL products you purchased, you will use the **tar** command for the following components:

- **4glid** (Interactive Debugger)
 - **4glrds** (4GL Rapid Development System)
 - **c4gl** (4GL C Compiler)
5. Enter the installation command for the first 4GL product you want to install.

For example, to install the first product listed in the following table, enter `./install4db`. You will perform steps 4 through 8 for each of the products you purchased.

Product	Installation Command
INFORMIX-4GL Interactive Debugger	<code>./install4db</code>
INFORMIX-4GL C Compiler	<code>./install4gl</code>
INFORMIX-4GL Rapid Development System	<code>./install4gp</code>

The following message appears on the screen:

```
Installation Script
This installation procedure must be run by root (super-
user). It will change the owner, group, and mode of all
files of this package in this directory. There must be a
user "informix" and a group "informix" known to the
system.
Press RETURN to continue,
or the interrupt key (usually CTRL-C or DEL) to abort.
```

6. Press RETURN to continue the installation procedure.

The following prompt appears:

```
Enter your serial number (e.g., INF#X999999) >
```

7. Enter the 11-character serial number located on your serial number keycard.

The serial number is 3 uppercase letters, followed by a pound sign (#), followed by 1 uppercase letter and 6 digits.

The following prompt appears:

```
Enter your serial number KEY (uppercase letters only)>
```

8. Enter the 6-letter key from the serial number keycard.

You then see a message similar to the following:

```
WARNING!  
This software, and its authorized use and number of users,  
are subject to the applicable license agreement with  
Informix Software, Inc. If the number of users exceeds the  
licensed number, the excess users may be prevented from  
using the software. UNAUTHORIZED USE OR COPYING MAY  
SUBJECT YOU AND YOUR COMPANY TO SEVERE CIVIL AND CRIMINAL  
LIABILITIES.
```

If your software is licensed for use by an unlimited number of simultaneous users, you see a message to that effect.

9. Press RETURN to begin the installation.

A series of messages appears on the screen as each directory is installed:

```
Installing directory .  
Installing directory bin  
Installing directory lib  
.  
.  
.
```

The following message tells you that your IBM Informix product is fully installed:

```
Installation of <product> complete
```

After this message appears, you see the shell prompt, indicating completion of installation.

10. Repeat steps 4 through 8 until each of the files has been executed.
11. Log out as **root** after you complete product installation.

Notices

IBM may not offer the products, services, or features discussed in this document in all countries. Consult your local IBM representative for information on the products and services currently available in your area. Any reference to an IBM product, program, or service is not intended to state or imply that only that IBM product, program, or service may be used. Any functionally equivalent product, program, or service that does not infringe any IBM intellectual property right may be used instead. However, it is the user's responsibility to evaluate and verify the operation of any non-IBM product, program, or service.

IBM may have patents or pending patent applications covering subject matter described in this document. The furnishing of this document does not give you any license to these patents. You can send license inquiries, in writing, to:

IBM Director of Licensing
IBM Corporation
North Castle Drive
Armonk, NY 10504-1785
U.S.A.

For license inquiries regarding double-byte (DBCS) information, contact the IBM Intellectual Property Department in your country or send inquiries, in writing, to:

IBM World Trade Asia Corporation
Licensing
2-31 Roppongi 3-chome, Minato-ku
Tokyo 106-0032, Japan

The following paragraph does not apply to the United Kingdom or any other country where such provisions are inconsistent with local law:

INTERNATIONAL BUSINESS MACHINES CORPORATION PROVIDES THIS PUBLICATION "AS IS" WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESS OR IMPLIED, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF NON-INFRINGEMENT, MERCHANTABILITY OR FITNESS FOR A PARTICULAR PURPOSE. Some states do not allow disclaimer of express or implied warranties in certain transactions, therefore, this statement may not apply to you.

This information could include technical inaccuracies or typographical errors. Changes are periodically made to the information herein; these changes will be incorporated in new editions of the publication. IBM may make improvements and/or changes in the product(s) and/or the program(s) described in this publication at any time without notice.

Any references in this information to non-IBM Web sites are provided for convenience only and do not in any manner serve as an endorsement of those Web sites. The materials at those Web sites are not part of the materials for this IBM product and use of those Web sites is at your own risk.

IBM may use or distribute any of the information you supply in any way it believes appropriate without incurring any obligation to you.

Licensees of this program who wish to have information about it for the purpose of enabling: (i) the exchange of information between independently created programs and other programs (including this one) and (ii) the mutual use of the information which has been exchanged, should contact:

IBM Corporation
J74/G4
555 Bailey Ave
P.O. Box 49023
San Jose, CA 95161-9023
U.S.A.

Such information may be available, subject to appropriate terms and conditions, including in some cases, payment of a fee.

The licensed program described in this information and all licensed material available for it are provided by IBM under terms of the IBM Customer Agreement, IBM International Program License Agreement, or any equivalent agreement between us.

Information concerning non-IBM products was obtained from the suppliers of those products, their published announcements or other publicly available sources. IBM has not tested those products and cannot confirm the accuracy of performance, compatibility or any other claims related to non-IBM products. Questions on the capabilities of non-IBM products should be addressed to the suppliers of those products.

This information contains examples of data and reports used in daily business operations. To illustrate them as completely as possible, the examples include the names of individuals, companies, brands, and products. All of these names are fictitious and any similarity to the names and addresses used by an actual business enterprise is entirely coincidental.

If you are viewing this information softcopy, the photographs and color illustrations may not appear.

Trademarks

AIX; DB2; DB2 Universal Database; Distributed Relational Database Architecture; NUMA-Q; OS/2, OS/390, and OS/400; IBM Informix[®]; C-ISAM[®]; Foundation.2000[™]; IBM Informix[®] 4GL; IBM Informix[®] DataBlade[®] Module; Client SDK[™]; Cloudscape[™]; Cloudsync[™]; IBM Informix[®] Connect; IBM Informix[®] Driver for JDBC; Dynamic Connect[™]; IBM Informix[®] Dynamic Scalable Architecture[™] (DSA); IBM Informix[®] Dynamic Server[™]; IBM Informix[®] Enterprise Gateway Manager (Enterprise Gateway Manager); IBM Informix[®] Extended Parallel Server[™]; i.Financial Services[™]; J/Foundation[™]; MaxConnect[™]; Object Translator[™]; Red Brick Decision Server[™]; IBM Informix[®] SE; IBM Informix[®] SQL; InformiXML[™]; RedBack[®]; SystemBuilder[™]; U2[™]; UniData[®]; UniVerse[®]; wintegrate[®] are trademarks or registered trademarks of International Business Machines Corporation.

Java and all Java-based trademarks and logos are trademarks or registered trademarks of Sun Microsystems, Inc. in the United States and other countries.

Windows, Windows NT, and Excel are either registered trademarks or trademarks of Microsoft Corporation in the United States and/or other countries.

Trademarks

UNIX is a registered trademark in the United States and other countries licensed exclusively through X/Open Company Limited.

Other company, product, and service names used in this publication may be trademarks or service marks of others.